



Installation manual of EcoChange

Package version

2019/12/4

[EcoChange Installation procedure]

Table of contents

Installation overview	1
PC that can use Eco Change	2
Hardware specifications.....	2
OS (Operating System)	2
Network environment.....	2
Required software	2
Printer	2
Install required software	3
Install Adobe Reader.....	3
Install EcoChange.....	4
Download the installer.....	4
Install EcoChange	5
Check EcoChange startup.....	9
In the case of the test server.....	9
Create parameter file (first time only).....	10
Log in to EcoChange.	11
Uninstall (delete) EcoChange	12
Remove from control panel	12
Programs and Features.....	13
Deleting EcoChange folder	14
Deleting a library	15

Installation overview

This section explains how to install EcoChange on your PC and use it.

- Check the PC to use EcoChange.
- Check and install the software required to use EcoChange.
- Confirmation of EcoChange startup

PC that can use Eco Change

Hardware specifications

CPU Intel Core i Series or higher recommended

Memory 2GB or more

HDD 100MB or more (EcoChange operation required capacity)

* Separate EDI data download area is required

OS (Operating System)

Windows7 or later recommended (Japanese / English) * **Supports 64-bit version only.**

* Please contact us if you want to run on Linux.

Network environment

Lines that limit communication speed due to increased communication volume are not recommended/Wired LAN connection recommended between PC and router (Wi-Fi connection not recommended)

Required software

Adobe Acrobat Reader version 7 or later (required only when issuing a PDF form)

Printer

Necessary when printing PDF forms. Laser printer recommended..

(Inkjet is not recommended due to unclear bar code printing)

Install required software


Install the required software that is not installed.

Install Adobe Reader


If Adobe Reader is not installed.

Go to <https://get.adobe.com/reader/>.

Uncheck.




Run according to
the screen.



Allow user account control and install.

* Click "Yes".




Install EcoChange

Install EcoChange main unit.

Download the installer


Download the EcoChange installer from the URL distributed with your account.



Download the setup program to any location.




Install EcoChange

Launch the downloaded installer and follow the instructions to install EcoChange.








Cancel

< Back



Next >



Yes

No

[Change when these notifications appear](#)



Check EcoChange startup.

Check EcoChange startup.


Double-click shortcut of EcoChange.



In the case of the test server

If you connect to a test server, a certificate error may be displayed.

Click "Continue to this website (not recommended)".




After this, a dialog appears asking whether to continue. Click "Continue".





Create parameter file (first time only)

The parameter file creation screen is displayed only at the first startup.

In the URL field , enter the EcoChange URL (Previous versions ,distributed with your account)




Please click "OK" ..



Log in to EcoChange.

Enter the company code, user ID, and password registered in EcoChange.

* The company code, user ID, and password will be contacted after registration.



EcoChange menu screen is displayed.



This screen is the supplier's screen, but for buyers, the buyer's menu is displayed.

This completes the installation of EcoChange.



Uninstall (delete) EcoChange

How to uninstall (delete) EcoChange from your PC.

Remove from control panel


Open the Control Panel and select “Programs and Features”.

Control panel




Programs and Features

When the list of programs and functions is displayed, check "EcoChange" from the list.




Right-click "EcoChange" on the list and select "Uninstall" from the menu.



Deleting EcoChange folder

The EcoChange program will be uninstalled as above, but the EcoChange folder that stores settings etc. remains locally. Delete "C:\ ecochange".




* If the EcoChange folder has been changed, use the following method to check the new folder location.

1. From the EcoChange mail screen ,select System(s) – Change System Folder (H)



2. The current system folder path is displayed in the system folder selection dialog.



Deleting a library

Delete "C:\Users\user name\EcoChange".

